


Title

DLL_Surface_Cpp_ReliefTypeDiffractionSurface

Author

Csilla Timar-Fulep

Brief Description



Overview

This User-Defined Surface DLL provides a realistic model of relief-type diffractive lenses based on zone-decomposition. Using zone-decomposition, diffraction into multiple orders can be accurately considered at once, and this method inherently accounts for wavelength dispersion and diffraction efficiency by modelling the actual shape of the diffractive element. Application examples include the creation of advanced intraocular lens models, where the different orders are designed to provide sharp vision for multiple viewing distances, thereby substituting accommodation of the natural crystalline lens.

[Realistic modeling of relief-type diffractive intraocular lenses using User-Defined Surface DLLs – Knowledgebase \(zemax.com\)](#)

Code Exchange Type

DLL Surface

Language

Cpp

Updates

Date	Version	OpticStudio version	Comment
20220715	1.0	22.2	Creation

Instructions

1. Installation

To install the User-Defined Surface DLL, copy the .dll file to the {Zemax}\DLL\Surfaces folder. OpticStudio will have to be restarted to be able to use the DLL.

2. How to use

To use the DLL, open a sequential file in which you would like to use the relief-type diffractive surface. Change the surface type to User Defined and select the DLL.